

> Our technology. Your success.





September 2015






KSB EasySelect® - Guided Tour List of contents

- 1. Step by Step to the Right Pump
- 2. Finding the right valve the easy way





Start

- The navigation bar is available during the entire KSB EasySelect[®] session.
- (2) Choose how to start here.
- (3) Click on the button "Go" or " " (on the navigation bar) to start your product selection.






Graphical Selection of "Segment"

- "Back" button
- Select the segment by clicking on its button (e.g. "Building services").
- (3) Instructions are shown on each page.






Graphical selection of general application

(1) Select the general application






Graphical selection of application

- Select the **application** by clicking on the button (e.g. "District heating")
- (2) You can switch between **general** applications with the register tabs.





KSB EasySelect® - Product selection


KSB EasySelect® - Guided Tour

Step by Step to the Right Pump

Product selection

- (1) Step 1: Input the operating point here. There are various tools to assist the input (e.g. pipe calculator).
- (2) On the register tab "Options" you can specify more requirements.






Step by Step to the Right Pump

Product selection

- (1) Step 2: Optionally select product types or specific products. The products recommended by KSB for the application are automatically preselected.
- Click on the icon for more product information.
- (2) Step 3: Click on the button "" or "Hydraulic search" to find the appropriate KSB solution.






Solution suggestion

- (1) The **KSB recommendation** is shown with its key information such as hydraulic data, curve and product data.
- (2) On the register tab "Alternatives" you can see additional pump sizes which fit your requirements. You can compare pump curves together on one diagram on the "Performance curves" tab.
- (3) Click on the button "Select" or " ocontinue configuration of the selected solution.






Step by Step to the Right Pump

Configuration overview

- This window shows a summary of the current configuration.
- (2) By clicking on "Select accessories" you can find accessories which match the configured product. With the "Change" button you can modify the product configuration.
- (3) Click on " ? " to continue to the output page.






Step by Step to the Right Pump

Price sheet

- (1) **Price overview** for the configured product
- (2) Click on " output page.






Output

- (1) Click on the desired **technical documentation** to get a preview in
 Acrobat Reader, where you also
 can **print or save** the document.
- **Delete** items with this icon.
- (2) Output of **CAD files** in over 40 different formats sent via e-mail.





Output

- (1) Switch the **document language** here
- (2) Use the "" button to return to the start page to add **new items** or to **stop** KSB EasySelect[®].






KSB EasySelect® - Guided Tour

List of contents

- 1. Step by Step to the Right Pump
- 2. Finding the right valve the easy way






Start

- (1) Choose how to start your "Valve selection" here.
- (2) Click on the button "Go" or " " (on the navigation bar) to start your valve selection.






Valve selection

- (1) Step 1: Input the operating point here.
- Optional selection by **design**
- Step 2: Click on one of the lines in the product list.
- Click on the icon for more **product** information
- (4) Step 3: Click on the button ">" or "Select" to find the appropriate KSB solution.






General design

- (1) On the **general design** page you can define the valve design.
- (2) Here is an overview of the **pressure limits**.
- (3) Click on " " to continue to the actuator selection page.






Actuator selection

- (1) Here you can select an **actuator** for the selected valve.
- (2) Click on " " to select automation accessories.






Automation accessory selection

- (1) Here, you can choose accessories for the selected drive.
- (2) Click on " > " to access the Configuration Summary.






KSB EasySelect® - Configuration overview

KSB EasySelect® - Guided Tour Finding the right valve the easy way

Configuration overview

- This window shows a summary of the current configuration.
- (2) Click on "Actuator selection" to select a suitable actuator and control equipment for the current configuration. With the "Change" button you can modify the product configuration.
- (3) Click on " o continue to the price sheet.






Price sheet

- (1) **Price overview** for the configured product
- (2) Click on " " to continue to the output page.





Output

- (1) Click on the desired **technical documentation** to get a preview in Acrobat Reader, where you also can **print or save** the document.
- (2) Switch the **document language** here
- (3) Use the "" button to return to the start page to add **new items** or to **stop** KSB EasySelect®.

